



You are reading an interactive PDF. If you are reading it in Adobe's Acrobat reader, you will be able to take advantage of links: where text is blue, you can jump to the next instruction. In addition you can use print buttons like the one on the right.

If this PDF has opened in Full Screen mode, you can quit by pressing Alt and F4, or press escape to view in normal mode.

Click [here](#) to start.



MIDI set-up in Sibelius 3 under Microsoft Windows

Making sure Sibelius is up-to-date

Before following any of the instructions in this document, you need to make sure that Sibelius is completely up to date. The latest version of Sibelius is Sibelius 3.1.3.

To check which version of Sibelius you have, click on Help and then About Sibelius. You'll see a splash screen like the one on the right and can work out which exact version you have.

If you don't already have version 3.1.3 and you're online, you can download a *free* update from www.sibelius.com/helpcenter: click on the More Info button under updates. Make sure you follow the instructions there carefully.

If you intend to use the Kontakt player for playback with Sibelius 3, you can also download the latest update to the player from this same website.



Once you've made sure you have the latest version of Sibelius, click [here](#) to proceed with setting up your MIDI devices.





MIDI set-up in Sibelius 3 under Microsoft Windows

Setting up MIDI in Sibelius is the first thing you need to do before you use it. Once you've set up MIDI correctly once, you won't have to do it again unless you change the MIDI devices you're using.

The way you set your MIDI up depends on what devices you have. Choose from the kind of set-up that you want to use:

Playing back through my computer speakers using the computer's sounds

Use this option when you don't have a MIDI keyboard to attach at all

Playing back through my computer speakers but recording with a keyboard

Use this option when you have a controller keyboard that doesn't have its own sounds or speakers.

Playing back through my computer speakers using Kontakt Player

Use this option when you want to use Kontakt Silver or Gold that comes with Sibelius 3

Playing back and recording through my MIDI keyboard

Use this option when you want to record and playback on your MIDI keyboard (the MIDI keyboard must have its own sounds and speakers or headphones).

Playing back through my Sound Module

This option will actually take you to playing through a MIDI keyboard, because it's a very similar thing.



If your problem is fixed, click [here](#) to close this file, or [here](#) to return to the first page

Playback through your computer speakers using the computer's sounds

Almost all PC soundcards come with their own MIDI synthesiser or use Microsoft's own GS Wavetable SW Synth.

Open Play > Devices and have a look under the Playback Devices. The magic word you're looking for is "Synth", which means that the computer is going to make the sounds for you.


If you *have no Synth listed*, the likelihood is that Windows or your soundcard is not installed properly. Check for driver updates on your soundcard manufacturer's website and contact Sibelius for help via the website.

Once you have located the Synth in the list, press the test button. You should hear a scale played through your computer speakers. If you don't, click [here](#).

Now we've ascertained that the Synth is working fine, we want to make sure it doesn't conflict with any other MIDI drivers on your computer.

Under the Use column, make sure the Synth is set to Yes, and *everything else* is set to No.

Once you've done this you can close the dialog, and your scores should play perfectly. If they don't, try opening the Mixer and click Reset Sounds.



The screenshot shows the 'Devices' dialog box in Windows. The 'Playback Devices' section is active, displaying a list of MIDI devices. The 'Microsoft GS Wavetable SW Synth' is highlighted, and its 'Use' column is set to 'Yes'. The 'Test' button for this device is also highlighted. The 'Input Device' section is visible below, showing a list of input devices including '1: Roland SC-8820'. The 'MIDI Thru' checkbox is checked.

Device	Test	Use	Sound Set	Latency (ms)
1:Roland SC-8820 PART B	Test	No	Roland SC-8820	0
1:Roland SC-8820 MIDI OUT	Test	No	General MIDI	0
EDIROL UA-20 MIDI OUT	Test	No	General MIDI	0
MPU-401	Test	No	General MIDI	0
Microsoft GS Wavetable SW Synth	Test	Yes	General MIDI	0




If your problem is fixed, click [here](#) to close this file, or [here](#) to return to the first page

Playback through your computer speakers using the computer's sounds

If your MIDI Synth seems to be silent, it could be that you've got it muted.


In the taskbar at the bottom right corner of the screen, double-click the little speaker icon to open the Master Volume/Mixer window.



If you can't see a volume slider labelled "SW Synth" or "MIDI" or similar, click Options then Advanced Controls (you may need to enable the slider within Options > Properties first).

Make sure that the volume is turned all the way up, and that there *isn't* a tick in the Mute checkbox.

Once it is turned on here, you should be able to hear it in Sibelius.
Click [here](#) to go back to the playback page.



If your problem is fixed, click [here](#) to close this file, or [here](#) to return to the first page

Playback through your computer speakers using the computer's sounds but recording with a controller keyboard

Set up playback first:

Almost all PC soundcards come with their own MIDI synthesiser or use Microsoft's own GS Wavetable SW Synth.

Open Play > Devices and have a look under the Playback Devices. The magic word you're looking for is "Synth", which means that the computer is going to make the sounds for you.

If you *have no Synth listed*, the likelihood is that Windows or your soundcard is not installed properly. Check for driver updates on your soundcard manufacturer's website and contact Sibelius for help via the website.

Once you have located the Synth in the list, press the test button. You should hear a scale played through your computer speakers. If you don't, click [here](#).

Now we've ascertained that the Synth is working fine, we want to make sure it doesn't conflict with any other MIDI drivers on your computer.

Under the Use column, make sure the Synth is set to Yes, and *everything else* is set to No.

Once you've done this you can close the dialog, and your scores should play perfectly. If they don't, try opening the Mixer and click Reset Sounds.

Next we need to set up your keyboard to record—click [here](#).

Devices

Playback Devices

Please click each MIDI device's Test button to see if you can hear it.
Set Use to Yes for one device and No for the others (unless you know you can use more than one at once). Also set Sound Set, which is normally the device name.

Device	Test	Use	Sound Set	Latency (ms)
1:Roland SC-8820 PART B	Test	No	Roland SC-8820	0
1:Roland SC-8820 MIDI OUT	Test	No	General MIDI	0
EDIROL UA-20 MIDI OUT	Test	No	General MIDI	0
MPU-401	Test	No	General MIDI	0
Microsoft GS Wavetable SW Synth	Test	Yes	General MIDI	0

Input Device

1. Highlight your input device, e.g. MIDI keyboard. (Typically this is the name of the port your keyboard is plugged in to.)
2. Try playing on your MIDI keyboard (or other input device); this indicator should light up.
3. Set MIDI Thru if your input device is silent. (This will make it play through another device.)

1:Roland SC-8820
1:Roland SC-8820 MIDI IN
EDIROL UA-20 MIDI IN
MPU-401

MIDI Thru

Play in Background... Find New Devices OK

Note that you can't use the Kontakt Player supplied with Sibelius for live recording. If you want to record live and later playback with Kontakt, set-up as described [here](#), and later change your set-up to use Kontakt as described [here](#).




If your problem is fixed, click [here](#) to close this file, or [here](#) to return to the first page

Playback through your computer speakers using the computer's sounds but recording with a controller keyboard

If your MIDI Synth seems to be silent, it could be that you've got it muted.


In the taskbar at the bottom right corner of the screen, double-click the little speaker icon to open the Master Volume/Mixer window.



If you can't see a volume slider labelled "SW Synth" or "MIDI" or similar, click Options then Advanced Controls (you may need to enable the slider within Options > Properties first).

Make sure that the volume is turned all the way up, and that there *isn't* a tick in the Mute checkbox.

Once it is turned on here, you should be able to hear it in Sibelius.
Click [here](#) to go back to the playback page.



If your problem is fixed, click [here](#) to close this file, or [here](#) to return to the first page

Playback through your computer speakers using the computer's sounds but recording with a controller keyboard

How will you connect your keyboard to your PC?

Via a breakout cable

A breakout cable is a cable which plugs into the joystick port of your computer's soundcard at one end, and to the MIDI in and out ports in your MIDI keyboard.



Via a USB to MIDI interface

A USB to MIDI interface plugs into the USB port on your PC. It then connects directly to the MIDI ports on your keyboard or allows MIDI cables to be attached to it.



Directly to my keyboard via a USB cable

Your keyboard should have been supplied with a USB cable and the necessary drivers on a CD-Rom.

If you're not sure which kind of connection to use, or haven't yet purchased a cable to connect your MIDI keyboard and PC, visit the store where you bought Sibelius to ask for advice.

If you have not yet set up your MIDI to playback correctly, it's important you do that first. Click [here](#) to go through that process.



If your problem is fixed, click [here](#) to close this file, or [here](#) to return to the first page

Playback through your computer speakers using the computer's sounds but recording with a controller keyboard

Connecting via a breakout cable:

This end of the breakout cable should be connected to your joystick port on the back of your PC. If there is an extra (female) plug, that's to allow you to leave your MIDI cables in and use a joystick at the same time.

These two MIDI plugs should be inserted into your keyboard. The one marked OUT goes to the MIDI IN port on your keyboard, if it has one (many controller keyboards don't). The one marked IN goes to the MIDI OUT port on your keyboard.



If after testing MIDI input this doesn't work, try swapping the cables over. Sometimes they are incorrectly labelled.

In Sibelius, go to Play > Devices. Under Input Device you are looking for either MPU-401 or the name of your soundcard and the words MIDI IN.

If this Input Device does not appear or do not work, you need to update your soundcard drivers from the manufacturer's website.

Select the correct device and play a few notes on your MIDI keyboard—the indicator will light up. MIDI in is working correctly! Check that MIDI Thru is ticked.

If you want to play directly in Sibelius, click on a staff of the instrument you would like to play back, then press Escape. This will load the correct sound and allow you to play on your keyboard.



If your problem is fixed, click [here](#) to close this file, or [here](#) to return to the first page

Playback through your computer speakers using the computer's sounds but recording with a controller keyboard

Connecting via a USB MIDI interface

In the packaging that came with your USB MIDI interface, there should be an instruction manual and a CD-Rom with the drivers on it. If you do not have this, look up the manufacturer's website and download the correct driver for your version of Windows.

Using the CD-Rom or downloaded file, install the drivers for your interface following the manufacturer's instructions. Plug the interface into your computer's USB port and into the keyboard's MIDI out port, following the instructions. Finally, restart your computer.

Before you run Sibelius, make sure that your USB interface is always connected and that your keyboard is turned on.

In Sibelius, go to Play > Devices. Under Input Device look for the name of your USB MIDI interface.

Once you have highlighted it by clicking on it, play a few notes on your keyboard. The little green light will flash which means your keyboard is correctly connected! Leave MIDI Thru ticked.

If you do not get the green light, your MIDI drivers may need to be updated or you may have wrong drivers for your version of Windows. Check on your USB MIDI Interface manufacturer's website.



Input Device

1. Highlight your input device, e.g. MIDI keyboard. (Typically this is the name of the port your keyboard is plugged in to.)
2. Try playing on your MIDI keyboard (or other input device): this indicator should light up.
3. Set MIDI Thru if your input device is silent. (This will make it play through another device.)

1: Roland SC-8820
1: Roland SC-8820 MIDI IN
MPU-401

MIDI Thru

A screenshot of the Sibelius 'Input Device' dialog box. The dialog box has a title bar 'Input Device' and a list of input devices. The first three items are '1: Roland SC-8820', '1: Roland SC-8820 MIDI IN', and 'MPU-401'. The second item is highlighted with a blue background. To the right of the list is a small black rectangular indicator light. Below the list is a checkbox labeled 'MIDI Thru' which is checked. Three orange arrows point from the text instructions to the corresponding elements in the dialog box: the first arrow points to the list of devices, the second arrow points to the indicator light, and the third arrow points to the 'MIDI Thru' checkbox.

If your problem is fixed, click [here](#) to close this file, or [here](#) to return to the first page

Playback through your computer speakers using the computer's sounds but recording with a controller keyboard

Connecting via a USB Cable

If your keyboard connects directly to your computer via a USB cable, in the packaging that came with your keyboard, there should be an instruction manual and a CD-Rom with the drivers on it. If you do not have this, look up the manufacturer's website and download the correct driver for your version of Windows.

Using the CD-Rom or downloaded file, install the drivers for your keyboard following the manufacturer's instructions. Finally, restart your computer.

Before you run Sibelius, always make sure that your keyboard is connected and turned on.

In Sibelius, go to Play > Devices. Under Input Device look for the name of your keyboard.

Once you have highlighted it by clicking on it, play a few notes on your keyboard. The little green light will flash which means your keyboard is correctly connected! Leave MIDI Thru ticked.

If you do not get the green light, your MIDI drivers may need to be updated or you may have wrong drivers for your version of Windows. Check on your USB MIDI Interface manufacturer's website.



Input Device

1. Highlight your input device, e.g. MIDI keyboard. (Typically this is the name of the port your keyboard is plugged in to.)
2. Try playing on your MIDI keyboard (or other input device): this indicator should light up.
3. Set MIDI Thru if your input device is silent. (This will make it play through another device.)

1: Roland SC-8820
1: Roland SC-8820 MIDI IN
MPU-401

MIDI Thru



If your problem is fixed, click [here](#) to close this file, or [here](#) to return to the first page

Playback through your computer speakers using the Kontakt Player

Setting up the Kontakt Player for playback

The first thing to note is that the Kontakt player is **not** intended for live recording. It is intended for great quality playback and for saving your scores as audio files.

If you want to record from a MIDI keyboard with sounds generated in your computer, click [here](#).



To set up the Kontakt Player in Sibelius, go to Play > Devices. The Kontakt Player should be at the top of the list. If it isn't, click [here](#).

Click the Test button next to the Kontakt Player. It should load a clarinet sample and play a scale. If it doesn't, click [here](#).

So that Kontakt doesn't conflict with any other drivers on your computer, change it to Yes in the Use column and change all other devices to No. Make sure that you scroll right to the bottom of the list.

Close this dialog and open the Mixer by pressing M. Make sure the right hand side of the mixer is open by clicking the arrow button if necessary and then click Reset Sounds and say Yes. All samples will be loaded, which may take some time.

Your score should now playback using Kontakt's sounds, and is ready for Save As Audio.



If your problem is fixed, click [here](#) to close this file, or [here](#) to return to the first page

Playback through your computer speakers using the Kontakt Player

Kontakt doesn't show up in Playback Devices

You may not have chosen to install Kontakt when you installed Sibelius 3, or you may have installed it while logged in as another user, in which case it is unusable.

Put your Sibelius 3 CD-Rom in your CD-Rom drive, and choose Install Kontakt Player. This takes some time and the progress bar may not move—just wait for it to complete.

You may also like to consider downloading updates for the Kontakt Player if you didn't do it earlier by clicking [here](#).

Kontakt Player shows up but doesn't play back

Kontakt Player plays back through your computer speakers, so as obvious as it may sound, make sure that you have them turned on and up before doing anything else. Kontakt samples are uncompressed and therefore naturally quieter than the average MIDI synth.

If Kontakt still won't play back, uninstall it, and then reinstall it as described above. Make sure that you are logged into Windows as the same user as you will be when you use Sibelius. If you can't do this because you're on, for example, a school network with security, talk to your IT manager for a solution.



Click [here](#) to return to the Kontakt playback page.



If your problem is fixed, click [here](#) to close this file, or [here](#) to return to the first page

Playing back and recording with a MIDI keyboard

How will you connect your keyboard to your PC?

Via a breakout cable

A breakout cable is a cable which plugs into the joystick port of your computer's soundcard at one end, and to the MIDI in and out ports in your MIDI keyboard.



Via a USB to MIDI interface

A USB to MIDI interface plugs into the USB port on your PC. It then connects directly to the MIDI ports on your keyboard or allows MIDI cables to be attached to it.



Directly to my keyboard via a USB cable

Your keyboard should have been supplied with a USB cable and the necessary drivers on a CD-Rom.

If you're not sure which kind of connection to use, or haven't yet purchased a cable to connect your MIDI keyboard and PC, visit the store where you bought Sibelius to ask for advice.



If your problem is fixed, click [here](#) to close this file, or [here](#) to return to the first page

Playing back and recording with a MIDI keyboard

Connecting via a breakout cable:

This end of the breakout cable should be connected to your joystick port on the back of your PC. If there is an extra (female) plug, that's to allow you to leave your MIDI cables in and use a joystick at the same time.


These two MIDI plugs should be inserted into your keyboard. The one marked OUT goes to the MIDI IN port on your keyboard, if it has one (many controller keyboards don't). The one marked IN goes to the MIDI OUT port on your keyboard.

If after testing MIDI this doesn't work, try swapping the cables over. Sometimes they are incorrectly labelled.

In Sibelius, go to Play > Devices. Under Playback devices look for an MPU-401 driver or a driver which mentions the name of your Soundcard and the words MIDI out. Click the text button and confirm that a scale is played on your keyboard.

Under the Use column, check that *only* this driver is set to Yes, and change all other drivers to No, so there are no conflicts.

Your keyboard is now set up for playback: Click [here](#) to set it up for recording.



Devices

Playback Devices

Please click each MIDI device's Test button to see if you can hear it.
Set Use to Yes for one device and No for the others (unless you know you can use more than one at once). Also set Sound Set, which is normally the device name.

Device	Test	Use	Sound Set	Latency (ms)
Microsoft GS Wavetable SW Syr	Test	No	General MIDI	0
1:Roland SC-8820 PART A	Test	No	General MIDI	0
1:Roland SC-8820 PART B	Test	No	General MIDI	0
1:Roland SC-8820 MIDI OUT	Test	No	General MIDI	0
MPU-401	Test	Yes	General MIDI	0

If this Playback Device does not appear or do not work, you need to update your soundcard drivers from the manufacturer's website.



If your problem is fixed, click [here](#) to close this file, or [here](#) to return to the first page

Playing back and recording with a MIDI keyboard

Breakout cable setup with a MIDI Keyboard continued

Setting up recording


Under Input Device you are looking for either MPU-401 or the name of your soundcard and the words MIDI IN.

If this Input Device does not appear or do not work, you need to update your soundcard drivers from the manufacturer's website.

Select the correct device and play a few notes on your MIDI keyboard—the indicator should light up. MIDI in is working correctly! Check that MIDI Thru is ticked.

If you want to play directly in Sibelius, click on a staff of the instrument you would like to play back, then press Escape. This will load the correct sound and allow you to play on your keyboard.

Close the dialog and start making music.



If your problem is fixed, click [here](#) to close this file, or [here](#) to return to the first page

Playing back and recording with a MIDI keyboard

Connecting your keyboard via a USB MIDI interface

In the packaging that came with your USB MIDI interface, there should be an instruction manual and a CD-Rom with the drivers on it. If you do not have this, look up the manufacturer's website and download the correct driver for your version of Windows.

Using the CD-Rom or downloaded file, install the drivers for your interface following the manufacturer's instructions. Plug the interface into your computer's USB port and into the keyboard's MIDI ports, following the instructions. Finally, restart your computer.


Before you run Sibelius, always make sure that your USB interface is connected and that your keyboard is turned on.

In Sibelius, go to Play > Devices. The name of your MIDI interface should be listed in both the Playback and Input devices.

Under playback devices, click on the test button next to the name of your MIDI interface. A scale will play on your keyboard. Once you've confirmed that it works, and to make sure it doesn't conflict with other drivers on your system, change it to Yes under the Use column and *all other* devices to No.

If you can't see your device in the list, the drivers are incorrect or are not correctly installed. Consult the manufacturer's website.

Now click [here](#) to set up MIDI in.



If you can see the device, but the Test button does not make a scale play back, try swapping the MIDI in and out cables, and check that your keyboard is in MIDI mode if it has a switch. If in doubt, refer to the manufacturer's website. Now click [here](#) to set up MIDI in.




Playing back and recording with a MIDI keyboard

Under Input Device look for the name of your USB MIDI interface.

Once you have highlighted it by clicking on it, play a few notes on your keyboard. The little green light will flash which means your keyboard is correctly connected! Leave MIDI Thru ticked.

If you do not get the green light, your MIDI drivers may need to be updated or you may have wrong drivers for your version of Windows. Check on your USB MIDI Interface manufacturer's website.

Alternatively your MIDI keyboard may have a special MIDI mode that it needs to be switched to. Check in the manual which came with your keyboard or on the manufacturer's website.



If your problem is fixed, click [here](#) to close this file, or [here](#) to return to the first page

Playback and recording with a MIDI keyboard connected directly by USB cable

Connecting via a USB Cable

If your keyboard connects directly to your computer via a USB cable, in the packaging that came with your keyboard, there should be an instruction manual and a CD-Rom with the drivers on it. If you do not have this, look up the manufacturer's website and download the correct driver for your version of Windows.

Using the CD-Rom or downloaded file, install the drivers for your keyboard following the manufacturer's instructions. Finally, restart your computer.

Before you run Sibelius, always make sure that your keyboard is connected and turned on.

In Sibelius, go to Play > Devices. You should be able to see the name of your keyboard under Playback Devices. Click on the Test button next to its name and your keyboard should play a scale.

Once you've confirmed it works, make sure that it says Yes next to your keyboard's name under the Use column and No for all other devices, so they can't conflict. Then click [here](#) to set MIDI Input.

If you can't see the name of your keyboard try clicking all Test buttons until your keyboard plays a scale. If none of them work, the driver has not been correctly installed: refer to your keyboard manufacturer's website.



Devices

Playback Devices

Please click each MIDI device's Test button to see if you can hear it.
Set Use to Yes for one device and No for the others (unless you know you can use more than one at once). Also set Sound Set, which is normally the device name.

Device	Test	Use	Sound Set	Latency (ms)
Kontakt Player	Test	No	Kontakt Gold	35
Microsoft GS Wavetable SW Sur	Test	No	General MIDI	0
1:Roland SC-8820 PART A	Test	Yes	Roland SC-8820	0
1:Roland SC-8820 PART B	Test	No	Roland SC-8820	0
1:Roland SC-8820 MIDI OUT	Test	No	General MIDI	0

If you can see your keyboard's name in the list but the test button does not work, check that your keyboard doesn't need to be switched to USB MIDI in mode in its manual. Try turning local MIDI control on and off and, of course, make sure that the volume is turned up on your keyboard! If it's still not working, refer to your keyboard manufacturer's website. If it is now working, click [here](#) to set MIDI Input.



Playback and recording with a MIDI keyboard connected directly by USB cable

Under Input Device look for the name of your keyboard.

Once you have highlighted it by clicking on it, play a few notes on your keyboard. The little green light will flash which means your keyboard is correctly connected! Leave MIDI Thru ticked.

If you do not get the green light, your MIDI drivers may need to be updated or you may have wrong drivers for your version of Windows. It could also be that the keyboard has a switch to change it to USB MIDI mode. Check the manual that came with your keyboard and if in doubt consult the keyboard manufacturer's website.

Input Device

1. Highlight your input device, e.g. MIDI keyboard. (Typically this is the name of the port your keyboard is plugged in to.)
2. Try playing on your MIDI keyboard (or other input device): this indicator should light up.
3. Set MIDI Thru if your input device is silent. (This will make it play through another device.)

1: Roland SC-8820
1: Roland SC-8820 MIDI IN
MPU-401

MIDI Thru



If your problem is fixed, click [here](#) to close this file, or [here](#) to return to the first page